

Vitrek V71 HiPot Controller

A Python/Flask web application for controlling the **Vitrek V71 Hi-Pot Tester** over USB (HID-to-UART) or RS-232. Runs test sequences, stores results in a local SQLite database, and exports to Excel for SharePoint sync. Built at [Juniper Design](#).

 **Print-ready PDF:** `docs/pdf/README.pdf`

Features

- **USB and RS-232 support** — USB via Silicon Labs CP2110 HID-to-UART DLL (SLABHIDtoUART.dll); RS-232 via pyserial
- **Full V7X command set** — ACW, DCW, IR, GB, CONT test steps; sequence management; live measurements
- **Web UI** — browser-based interface, no installation needed on operator machines (just open `http://localhost:5000`)
- **SQLite results database** — every test session and step result persisted locally
- **Excel export** — formatted, color-coded workbook per session or bulk; ready for SharePoint

Quick Start

1. Install dependencies

```
pip install -r requirements.txt
```

2. Connect the V71

- **USB:** Set `CONFIG MENU → INTERFACE = USB` on the V71 front panel. Connect the USB-B cable.
- **RS-232:** Set `CONFIG MENU → INTERFACE = RS232` and matching baud rate. Use a 9-wire null-modem cable.

3. Run the app

```
python app.py
```

Open `http://localhost:5000` in your browser.

Project Structure

- └─ app.py Flask web app + REST API + embedded UI
- └─ v71_driver.py Low-level USB/serial driver (ctypes + pyserial)
- └─ database.py SQLite schema and CRUD
- └─ excel_export.py openpyxl Excel workbook generator
- └─ requirements.txt
- └─ hipot_results.db SQLite database (auto-created on first run)
- └─ docs/
 - └─ V7x_Series_Operating_Manual.pdf

REST API

Method	Endpoint	Description
POST	/api/connect	Connect to V71 ({ "mode": "usb" } or { "mode": "serial", "port": "COM3", "baud": 115200 })
POST	/api/disconnect	Disconnect
GET	/api/status	Current connection + run state
POST	/api/run	Start a test sequence (see below)
POST	/api/abort	Abort running test
POST	/api/cont	Continue from HOLD step
GET	/api/live	Live VOLTS/AMPS/OHMS during a run
GET	/api/sessions	Recent test sessions
GET	/api/session/<id>	Session detail + step results
GET	/api/export	Download all sessions as Excel
GET	/api/export/<id>	Download single session as Excel

Example: run a test via API

```
POST /api/run
{
  "operator": "Jason",
  "part_number": "PCB-001",
  "serial_number": "SN-12345",
  "steps": [
    { "type": "ACW", "voltage": 1500, "ramp": 2, "dwell": 60, "max_leakage": 0.005 },
    { "type": "IR", "voltage": 500, "dwell": 60, "min_resistance": 100000000 },
    { "type": "GB", "current": 25, "dwell": 5, "max_ohm": 0.1 }
  ]
}
```

USB Communication Details

The V71 uses a **Silicon Labs CP2110 HID-to-UART bridge**. Communication is handled through:

- SLABHIDtoUART.dll + SLABHIDDevice.dll (x64 versions from software/drivers/)
- USB VID: 4292 (0x10C4), PID: 34869 (0x8835)
- UART config: 115200 baud, 8N1, RTS/CTS flow control
- Protocol: ASCII commands terminated with \r\n

Key commands (from Section 6 of the operating manual):

Command	Description
*IDN?	Identify device
*RST	Reset / clear
*ERR?	Read error register
NOSEQ	Clear active sequence
ADD,ACW,...	Add ACW test step
ADD,DCW,...	Add DCW test step
ADD,IR,...	Add IR test step
ADD,GB,...	Add Ground Bond step
ADD,CONT,...	Add Continuity step
RUN	Start active sequence
ABORT	Abort running sequence
RUN?	Query if running (0/1)
RSLT?	Overall result bitmask
STAT?	Per-step pass/fail string
STEPRSLT?,<n>	Detailed results for step n
MEASRSLT?,AMPS	Live current measurement
MEASRSLT?,VOLTS	Live voltage measurement

Excel Export

Each export workbook contains: - **Summary sheet** — all sessions with pass/fail, sortable/filterable - **Per-session sheets** — full step results with color coding (green=pass, red=fail)

The .xlsx file is suitable for direct upload or auto-sync to SharePoint.

Notes

- The DLL must be accessible at `software/drivers/USB_DLLs_and_Headers/USB_DLLs_and_Headers/x64/`
- The app must be compiled/run as **x64** to match the provided DLL architecture
- After a DUT breakdown event on USB, the V71 may disconnect and reconnect — the driver detects this and surfaces an error; simply reconnect from the UI
- RS-232 requires hardware handshaking (RTS/CTS) — ensure your cable is fully wired (9-wire null modem)